

# Alaris MNP Server

---

## User's Guide

version 2.2.0

---

Document Type: User's Guide

Date of Issue: 4/25/2025

---

Copyright © 2005 - 2025 Alarislabs Pte Ltd.  
All rights reserved.

The information contained in this document is the property of Alarislabs Pte Ltd. No part of this publication may be reproduced or copied in any form or by any means - graphic, electronic or mechanical including photocopying, recording, taping, or any other information storage and retrieval System - without written consent of Alarislabs Pte Ltd. No third party, organization or individual, is authorized to grant such permission.

The information provided in this document is for general informational purposes only. While we strive to ensure accuracy and completeness, the documentation may contain omissions, or may not reflect the most current updates or include all recent changes. Alarislabs Pte Ltd. cannot be held responsible for any inaccuracies or incomplete information contained in this manual. Users are encouraged to verify details and consult with the Alaris technical support team for the most up-to-date and comprehensive information ([support@alarislabs.com](mailto:support@alarislabs.com)). By using this manual, you acknowledge that you understand and accept these terms.

# Table of Contents

<b>1 MNP server overview .....</b>	<b>4</b>
<b>2 Account settings .....</b>	<b>5</b>
<b>3 Sources .....</b>	<b>6</b>
<b>4 Clients .....</b>	<b>12</b>
<b>5 Reselling API .....</b>	<b>15</b>
5.1 HTTP .....	15
5.2 ENUM .....	16
<b>6 HLR request rules .....</b>	<b>18</b>
<b>7 Settings .....</b>	<b>21</b>
<b>8 Users .....</b>	<b>22</b>
<b>9 Roles .....</b>	<b>24</b>

## 1 MNP server overview

*MNP server* is an add-on module of Alaris SMS Platform that serves to manage number portability and HLR reselling. It serves to configure supported HLR providers (sources), HLR request rules and HLR clients. To enable the module and make it available in the Alaris SMS Platform interface for HLR reselling purposes, contact your Account manager. For regular configuration of HLR request rules, submit a ticket on our HelpDesk.

To access the MNP server, proceed as follows:

1. Access the MNP server using a separate URL provided by the Alaris technical support team or the one registered by the System owner. For users that purchased the HLR reselling feature at Alaris SMS Platform, the MNP server can be accessed through the Alaris SMS Platform interface.

---


**NOTE:** For purchasing, contact your Account manager.

---

2. The interface contains the following pages: [Sources](#)<sup>[6]</sup>, [Clients](#)<sup>[12]</sup>, [HLR request rules](#)<sup>[18]</sup>, [Settings](#)<sup>[21]</sup>, [Users](#)<sup>[22]</sup> and [Roles](#)<sup>[24]</sup>. Each page (except [Settings](#)<sup>[21]</sup>) contains a table of records and the following buttons at the top:
  - a. *Refresh page*
  - b. *Export*: serves to export the table into an MS Excel file.
  - c. *Add new* (user, rule etc.): serves to add a new record.
3. Configure the settings as detailed below.

## 2 Account settings


The *Account settings* menu is available if the user has logged in using a separate URL provided by the Alaris technical support team. When accessed through Alaris SMS Platform interface, it is not displayed.



### Account settings

Use the *Dark theme* toggle to apply the dark theme. Select the interface language with the help of language switcher. Log out using the *Log out* button.

Click *Account settings* to be forwarded to *Your profile* page where personal information can be filled in.

A screenshot of the 'Your profile' page. The page has a sidebar on the left with the Alaris Labs logo and navigation items: 'MNP Configurator', 'Sources', 'Clients', 'Dipping rules', and 'Settings'. The main content area is titled 'Your profile' and shows a user icon and email 'kate@example.com'. Under 'Personal information', there are input fields for 'First name' (Kate), 'Last name', 'Email' (kate@example.com), and 'Login' (kate). There is a 'Page size' dropdown menu set to '25'. Under 'Password', there is a message 'We recommended that you change your password periodically' and a 'Change password' button. At the bottom, there are 'Save changes' and 'Cancel' buttons.

### Your profile

Select a value from the *Page size* list to define the number of records within one page on [Sources](#)<sup>[6]</sup>, [Clients](#)<sup>[12]</sup>, [HLR request rules](#)<sup>[18]</sup> shown by default.

Use the *Change password* button to set a new password.

### 3 Sources

The page allows adding a new HLR service that can be used in HLR request rules as an HLR source. The main table shows the existing sources that can be filtered with the help of the *Name* and *Type* filters.

Sources iana@alarislabs.com


Total: 20 Filter Refresh page Export Add new source

NAME	TYPE	HUNTSTOP	TTL
Esme	esme	false	0
GMS	gms	false	0
KA	akton	false	0
KA2	akton	true	0
MaksP_	generic_enum	false	0
MAksP	hgc_enum	false	0
mnp	mnp	true	3
MNP AP	mnp	false	0

Showing 1 - 20 Prev 1 Next Show rows 25

### Sources

✕



### Add new source

ENUM HTTP SS7 **MNP**

Name  
mnp

Type \*  
mnp

Cache all Only successful **Only specific**

Specify response code list to cache  
["1";"SUCCESS"]

Custom MNP: TRASH, UNALLOCATED, RCS\_CAPABLE, WA\_CAPABLE  
RCS\_CAPABLE

MNP active DB  
6

Reroute and keep MCCMNC

Huntstop

MCCMNC translation  
{"238001":"238002";"238003":"999999"}

MNP stage DB  
4

Cached response lifetime \*  
0

Reset

Submit

Close

### Add new source

To add a new service, click the *Add new source* button and configure the following fields (fields marked with an asterisk \* are required). Note that for some fields an example can be found by hovering over the field.

- Select the HLR service protocol in the top panel: *ENUM, HTTP, SS7, MNP*.
- *Name*: insert a unique provider name. The name will be used to configure HLR request rules. It is possible to add several sources with different names but of the same type. It may come in handy for configuration of the same HLR provider with different settings. For example, sources under *mitto\_1* and *mitto\_2* of the *mitto* type can be added with separate time-to-live values. Such a configuration allows separating sources if for some countries TTL must differ
- *Type*: select the provider type from the drop-down list. Basically, it is the list of supported HLR providers. The type is an internal hardcoded name in accordance with which a request to the provider is formed and sent as well as the provider's response is recognized

Based on the selected *Type*, the following additional fields appear.

- *Cache all, Only successful, Only specific*: select the appropriate value from the bar:
  - *Cache all*: all responses will be cached (selected by default).

- *Only successful*: when selected, the results will be placed to cache only if the HLR MCCMNC was successfully obtained.
- *Only specific*: specify the responses that must be cached in the field that appears below the bar. The suggested syntax is ["1", "SUCCESS"] - that is, comma-separated values in parentheses, enclosed in square brackets.
- *Do not use MCCMNC* (available if *Type=hlrlookups*): when enabled, only the *hlrResponseCode* value is taken from the vendor's response.
- *Custom MNP* (available if *Type=mnnp*): allows the user to select one of the fields at the MNP source level and return the number details received from the MNP to the client in response. Possible values are: *TRASH*, *UNALLOCATED*, *RCS\_CAPABLE*, *WA\_CAPABLE*. To return the data, select the appropriate fields (*trash*, *unallocated*, *is\_rcs\_capable*, *is\_wa\_capable*) in the *Response fields* list at the client level (for the HTTP client). For ENUM clients, contact the Alaris technical support team and provide the code MNP-516 to configure the ENUM response template.

---

**NOTE:** In order to use all fields, create separate MNP sources and specify the required sources in the HLR rule sequentially (*Choice list* field in [HLR request rules](#)<sup>[18]</sup>). Custom fields received from such sources will not be overwritten when requesting the next source. Additionally, new data must be imported into MNP databases in the following format (from a csv file): *prefix;boolean value*

for example:

`34123456>true`

- 
- *MNP active DB* (available if *Type=mnnp*): the number of the active in-memory DB to which the MNP base will be loaded.
  - *MNP stage DB* (available if *Type=mnnp*): the number of the inactive in-memory DB.

---

**NOTE:** If a single MNP database is used, it is recommended to leave the values empty. It should be noted that the MNP database loading pre-configuration is performed by the Alaris team.

- 
- *Cached response lifetime*: TTL, in seconds. The parameter defines the period to store the HLR results in cache for a specific number. For example, the parameter is set to 10 (seconds). A new request to number 3411111111 is received. Once HLR results are obtained from the HLR service, they are placed in cache. If within the following 10 seconds a request to the same number comes, no actual dipping will be performed but the previous results will be used. The minimum value is 0 (that is, no request will be cached). The maximum value is to be clarified with the Alaris technical support team to avoid memory overflow. Generally it is recommended to specify the value not greater than 604800 (a week)
  - *Huntstop*: a huntstop option. Even if the HLR source returns an unsuccessful response (for example, with no HLR MCCMNC in it), no further HLR source will be queried
  - *Reroute and keep MCCMNC*: when enabled, the next-in-line HLR source (if any) after the HLR source in question will be requested for the number additionally in order to obtain the HLR response code (*hlrResponseCode*). The HLR MCCMNC and the portability flag will be fetched from the HLR source with the enabled *Reroute and keep MCCMNC* flag that was last in the list. The option comes in handy when the first source is MNP, and provides the info about MCCMNC and portability flag, while the second source is regular HLR and supplies the HLR response code.

---

**NOTE:** Only the last HLR source will be mentioned in the EDR, therefore the HLR billing happens for the last HLR source only.

---

- *Provider response code list to cache*: the list of `hlrResponseCode` (as an array) for the HLR responses to be cached (applicable if *Only specific* is selected). Example: `["1", "SUCCESS"]`
- *Host address for local address*: specify the IP address available for the server scheme which will be used as the source IP address when sending queries if an IP address other than the HLR configurator IP address must be used
- *Status request delay* (available if *Type=unibell*, or *redsms*, or *redsms2*): serves to specify forced delay between requests (if not specified, the value of 2 seconds is used)

## HTTP-specific settings:

- *Source URL*: the provider's URL. For example: <http://127.0.0.1:5555/websmpp/hlr/lookup>  
In some cases (when the provider operates following a 2-step request algorithm) it is required to fill in the *URL for first request to provider* and *Status URL* parameters. In addition to the *Source URL* link some providers require the *MNP service domain* (domain) parameter to be passed in a request
- *Username/Password/API key/User email/Customer ID/Customer key (username)/Secret key (password)*: specify the credentials granted by the HLR provider
- *HTTP request timeout*: the period in seconds to expect the HLR service response. Once reached, the next-in-line HLR service will be used (if any). If a value is not specified, the value of the Default request timeout setting will be applied ([Settings](#)<sup>[21]</sup>).
- *Source GT*: global title (applicable to HLR over SS7)
- *MCC list to handle IMSI from response*: the list of MCCs for which first 6 digits are fetched from the `imsi` field (applicable to HLR over SS7). Example: `[262,302,352,354,467,503,751]`

## ENUM-specific settings:

- *Domain for NAPTR record*: the domain name of the ENUM HLR provider. Example: `e164.arpa`
- *IP address*: the IP address of the ENUM HLR provider
- *Port*: the port of the ENUM HLR provider
- *Number of attempts to request provider*: the number of retries to reach the provider's server. Must be greater than 0
- *Timeout for each try of requesting*: the timeout (in ms) to wait for a response from the DNS server

---

**NOTE:** If the request was resubmitted to the same provider by the parameters *Number of attempts to request provider* and *Timeout for each attempt of requesting*, interim HLR EDRs will be recorded.

---

- *Port for local address*: specify a source port from which requests will be sent out. It is recommended to leave the setting empty

## Translation-related settings:

- *Use fixed MCCMNC*: when the checkbox is selected and the HLR provider returns *type=fixed*, a fixed MCCMNC will be assigned (for example, for the *tmthttp* HLR service, it will be 999001; for the *netnumbercid* source, it will be 999999)
- *Use error code from error (E) field*: select to obtain values for the `hlrResponseCode` routing metric from the `e` field of the provider's response. When deselected, the values are fetched from the `gsmcode` field or the `pres` field if the `gsmcode` field is not available

- **Translate OCN to MCCMNC:** set translation rules to assign the MCCMNC as a pre-set one in accordance with the ocn value from the provider's response. The format must be JSON. Example: `{"8304":"302002", "8202":"302003"}` where for `ocn=8304` MCCMNC 302002 will be assigned
- **Use error code from Status field:** select to obtain values for the `hlrResponseCode` routing metric from the `status` dictionary of the provider's response. When deselected, the values are fetched from the `error` dictionary
- **Invalid number code:** specify a value (for example, 99) if it must be used as the `hlrResponseCode` routing metric provided that the HLR service returns `status_message=Invalid Number`
- **Response code source:** for `netnumber_mnis`: specify `nnti` or `nnci` to gather values for the `hlrResponseCode` routing metric from the corresponding field of the provider's response. Otherwise the values are parsed from the `status` field. For `mitto`: specify `absent` to gather values for the `hlrResponseCode` routing metric from the corresponding field of the provider's response. Specify `complex` to enable the logic as follows: if `absent` is not available in the HLR source response, no `hlrResponseCode` is assigned, if `absent` is returned as true, `hlrResponseCode` is set to 1, if `absent` is returned as false, `hlrResponseCode` will be fetched from `gsmCode` (or, if not available, from `response` with "r" prefix). Otherwise the values are parsed from the `gsmCode/response` fields.

For `tmolive`: specify `error` or `present` to gather values for the `hlrResponseCode` routing metric from the corresponding field of the provider's response. Otherwise the values are parsed from the `status` field.

For `xconnect` and `netnumbercid` types: specify a field from the provider's response (for example, `cic`) to fetch its values to `hlrResponseCode`.

- **MCCMNC translation map and MCCMNC translation map extra:** set mapping rules to assign the MCCMNC in accordance with the provider's response. The format must be JSON. Example: `{"724301":18, "724302": 54}`

where 724301 and 724302 are the resulting MCCMNCs and 18 and 54 are codes from the provider's response. To double-check from which fields the codes are collected, consult the Alaris technical support team

- **MCCMNC translation:** set translation rules to convert the MCCMNC from the provider's response to a pre-set one. The format must be JSON. Example: `{"238001":"238002", "238003": "999999"}`
- **Translate error code to MCCMNC:** set rules to assign the MCCMNC in accordance with the codes returned by the providers. The format must be JSON. Example: `{"0":"238002", "r1": "999999"}`




where `0` and `r1` are error codes and `238002` and `999999` are the final MCCMNCs. Note that the MCCMNC is assigned only if the MCCMNC cannot be parsed or found in the provider's response. To confirm from which fields values are obtained for particular HLR providers, contact the Alaris technical support team

- **Extra fields in response** (available if `Type=redsms`): when enabled, the `fields` field with the value `all` will be sent to the provider in the request. In this case, the provider's response contains the `mccmnc` field, from which the data is taken to define the HLR MCCMNC
- **Forced error code translation:** enable to assign the MCCMNC in accordance with the `Translate error code to MCCMNC` option even if the HLR MCCMNC was returned by the HLR service


- *Mapping carrier\_id from response to MCCMNC*: specify a JSON array to assign an MCCMNC in accordance with the carrier\_id value from the provider's response. Example: `{ "1" : "440050", "2" : "440020", "3" : "440010", "6" : "440011" }`
- *Custom translation (applicable to restcom)*: optional field, when filled in, the *MCCMNC translation* is not verified. Specify a JSON array to assign an MCCMNC in accordance with the *imsi* value (symbols from 3 to 5 of the field) from the provider's response. Example: `{ "123": "238002", "231": "238003" }`
- *Translate network name to MCCMNC*: specify a JSON array to assign an MCCMNC in accordance with the network name from the provider's response. Example: `{ "Algar Telecom" : "724032", "Claro" : "724005" }`
- *Inactive subscriber MCCMNC*: specify the MCCMNC which will be assigned as the HLR MCCMNC if *presence=false* in the provider's response. If left empty, no special translation takes place
- *Translate MNP code to MCCMNC*: set MCCMNC in accordance with the *mnpcode* field of the provider's response. The logic of assignment is as follows: the third, the fourth and the fifth digit of *mnpcode* is used to define the MCCMNC from the translation set.

Example: `{ "321" : "724005", "341" : "724002", "301" : "724018" }`




Suppose that the provider returned *mnpcode=703013100055*, then value *301* will be used for MCCMNC definition, which is *724018* based on the above example

Click *Close* to stop adding a new source. Click *Reset* to clear the form. Click *Submit* to add a new source. To edit an existing source, click the *Edit*  icon. A form similar to the *Add new source* panel will appear. To remove a source, click the *Delete*  button. A warning will appear: "Are you sure you want to permanently remove source?" Press *Cancel* to cancel the deletion or *Confirm* to proceed with the operation. To refresh the page, click the *Refresh*  button.

## 4 Clients



The *Clients* page serves to create a new HLR reselling client or manage the existing ones. The main table shows the available clients. To filter the table by the client name, click  *Filter*, unwrap the *Client product* list and either insert the product name, or select the product(s) from the list.

**Clients** tatiana@alarislabs.com

Total: 9  *Filter*  Refresh page  Export [+ Add new client](#)

LOGIN	CLIENT PRODUCT	INTERFACES	MAX SESSIONS
alaris	KA_HLR - hlr_adv	http smsrt	10000
alaris2	KA_cli - hlr	http	10000
AP	Alexander YouTube - HLR	http	1000
APCP	KA_HLR - adv2	http	1000

### Clients

To adjust the parameters of an existing client, click the *Edit*  button. Use the *Delete*  button to remove the record. A warning message will appear.

To add a new record, click the *Add new client* button. The mandatory parameters are as follows:

- *Login*: the client login that will be used for authentication if requests are to be sent over HTTP
- *Password*: the client password that will be used for authentication if requests are to be sent over HTTP. Apply the *Generate button* to generate the password
- *Client product*: select the HLR client product that has been created in the System. The requests received under the client record will be associated with the client product in order to use its rates and issue invoices. The parameter is optional and can be set to *None* if no client product must be assigned to client's requests. Use the *Filter* window to quick-filter and find the required product.
- *Interfaces*: select the protocols over which the client will send requests. The default value is HTTP. The possible values include *HTTP*, *ENUM*, *SMSRT* (the System value which is used for System configuration)
- *Remove leading zero from MNC*: select the flag if 5-digit MCCMNCs must be returned to the client (for example, 23801 instead of 238001)
- *Force result to 1*: if enabled, the result field in the response to the client will be forced to 1 when the number is recognized as ported (ported=1).
- *Max sessions*: the default value is 1000. The maximum number of session per client.
- *Response fields*: the field defines the list of fields to be returned to the client in response over HTTP. The default value includes:
  - *mccmnc*: the HLR MCCMNC (6-digit by default)
  - *result*: shows if the result is successful (0: yes, other values: no)
  - *ported*: the portability information (0: not ported, 1: ported)

- *source\_name*: the HLR service name (in case of several HLR services, the name of the last HLR service)
- *source\_type*: the HLR service type (in case of several HLR services, the type of the last HLR service)
- *dnis*: the destination address in e.164 format for which a query was processed
- *login*: the client login
- *system\_response\_code*: System response code values. Possible returned values (and general logic of their assigning) are as follows:

0 - the response code from the HLR provider is successful (the number is available in the network, it is valid etc.) and, if the provider returns an MCCMNC, the HLR MCCMNC is received

1 - the response code from the HLR provider is unsuccessful (for example, the number is unavailable or invalid), but an HLR MCCMNC was received

2 - the response code from the HLR provider is unsuccessful (for example, the number is unavailable or invalid) and no HLR MCCMNC was received

3 - the HLR request was unsuccessful (for example, no response was received from the provider or the provider response code is unknown to the System)

Note that System codes are not assigned to all HLR providers, and also assigning a value for different HLR providers is based on different fields from their responses. For more detailed logic description, contact the Alaris technical support team and provide the MNP-485 code and the HLR source type (for example, *netnumbercid*).

Extra fields to be added:

- *message\_id*: the identifier of the request (assigned by the client)
- *rate*: the client rate from the corresponding HLR client product
- *wireless*: if the number was found in the MNP database (0: no, 1: yes). Applicable to the *mnp* source only
- *cached*: if the result was obtained from the cache (0: no, 1: yes)
- *present, roaming*: if the number is present/if the number appears in roaming, respectively, over the HTTP protocol. To add information for an ENUM response, contact the Alaris technical support team and provide the code HLR-23. If the flags cannot be recognized from the source HLR response, the returned value will be *NA*. Other possible values: *yes, no*. The logic for fetching the *present* and *roaming* fields is added for some types of HLR sources and described below:
  - *mitto* - *present* is fetched from the *absent* field (if *absent=true*, then *present=no*, if *absent=no*, then *present=yes*); *roaming* is fetched from the the *roaming* field
  - *tyntec* - *present* is fetched from the *presence* field, *roaming* - from the *roaming* field
  - *xconnect* - *present* is taken from the *ns* field (if *ns=000* then *present=yes*; if *ns=001*, or *002*, or *003* then *present=no*), the *roaming* field is not recognized
  - *tmtlive* - *present* is taken from *present*, the *roaming* field is not recognized

- *infobip - present* is recognized from *{status}{groupName}* (if *groupName=DELIVERED*, then *present=yes*, if *groupName=UNDELIVERABLE*, then *present=no*), *roaming* - from the *roaming* field
- *netnumber\_mnis - present* is taken from *status*, the *roaming* field is not recognized
- *message*: contains extended information in regard to the requested number (for example, "Not valid response" if the HLR source response was not parsed by the HLR module, or "Vendor not found" if no HLR dipping rule was found suitable), may be absent from the response in case of success
- *context\_log*: full raw HLR source response proxied from the HLR source alongside internal information of parsing
- *providerResponseCode*: *hlrResponseCode* from the HLR source response
- *raw\_response*: serves to proxy the HLR vendor's raw response to clients
- *aux\_sources*: serves to transfer the full list of queried HLR vendors. If not specified, only the final queried vendor will be returned (for example, if the previous vendor did not return the MCCMNC or if the *Reroute and keep MCCMNC* flag was enabled).

## 5 Reselling API

This section details an API for working with third-party systems for HLR reselling. The supported protocols are HTTP (GET method) and ENUM.

### 5.1 HTTP

#### 1. HTTP example of a request (values highlighted in red must be replaced by actual values)

```
http://<HLRdomain>:port/hlr/mccmnc_request?  
login=<userlogin>&password=<userpass>&dnis=<dnis>&message_id=1&sender_id=Facebook&noCache=1
```

where

**HLRdomain**: HLR domain name

**port**: the HTTP listening port. The default value is 42081, can be overridden by internal configuration

**userlogin**: login

**userpass**: password

**dnis**: destination addresses in e.164 format

**message\_id**: request ID, may come in handy for troubleshooting purpose

**sender\_id**: sender ID, optional parameter

**noCache**: optional parameter, specify as 1 if a non-cached response must be obtained

#### 2. Response format

The fields returned in the response depend on the client's configuration as the list is configured with the help of the *Response fields* field. The fields enabled by default are described below.

##### 2.1. Successful response:

```
{  
  "mccmnc": "234001",  
  "result": 0,  
  "ported": 0,  
  "source_name": "some_mnp",  
  "source_type": "mnp",  
  "dnis": "34567891001",  
  "login": "login"  
}
```

where

**"mccmnc"**: 6-digit HLR MCCMNC

"result": shows if the result is successful (0 – yes, other values - no)

"ported": shows if the number is ported (0 - no, 1 - yes)

"source\_name": HLR source name

"source\_type": HLR source type

## 2.2. Unsuccessful response

An unsuccessful response does not contain an HLR MCCMNC

```
{
  "result": -1,
  "ported": 0,
  "source_name": "some_mnp",
  "source_type": "mnp",
  "dnis": "34567891001",
  "login": "login"
}
```

where

*result*: the following values can be returned for an unsuccessful response:

- -1 - No HLR MCCMNC found for the requested destination address (a non-empty response was received)
- -2 - No HLR rule was considered suitable
- -3 - No valid MCCMNC found for the requested destination address (for example, an empty response was received) or no translation rule is found for the returned error code/status
- -4; -6; -7 – System timeout
- -5 – the number is blacklisted

## 5.2 ENUM

### 1. ENUM example of a request (values highlighted in red must be replaced by actual values)

```
dig @<hlrAddress> -t NAPTR <reverseDnis>.<dummyDomainName> -p <port> +short
```

where

<hlrAddress>: the HLR server IP address

<reverseDnis>: the destination address number in reverse, separated by dots. For example, if the original number is 123456789, the *reverseDnis* will be 9.8.7.6.5.4.3.2.1

<dummyDomainName>: any domain name. For instance, e164enum.int.alarislabs.com

<port>: the ENUM listening port. The default value is 5053, can be overridden by internal configuration

### 2. Response format

The fields returned in the response depend on the system-wide internal configuration. Contact the Alaris technical support team to learn more or to configure a response template. Generally, the response contains the fields parsed from the provider's response.

### 2.1. Successful response

;; ANSWER SECTION:

```
2.8.1.0.1.4.2.2.6.2.1.2.e164.arpa. 0 IN NAPTR 100 10 "U" "E2U+pstn:tel"  
"!^(.*)$!country=null;operator=null;mcc=604;mnc=001;ported=false;err=0!" .
```

### 2.2. Unsuccessful response




A response does not contain an HLR MCCMNC:

```
3.2.4.3.6.0.4.6.2.0.2.e164.arpa. 0 IN NAPTR 100 10 "U" "E2U+pstn:tel"  
"!^(.*)$!country=null;operator=null;mcc=null;mnc=null;ported=false;err=-3!" .
```

The *err* values are the same as for the *result* values of the [HTTP reselling API](#) .

## 6 HLR request rules

The page serves to configure HLR request (dipping) rules. That is, which HLR services are to be used for number verification. Configuration can be prefix-, sender ID- and client-based.

The main table shows available rules that can be filtered with the help of the *Name*, *Choice list*, *Prefix list* and *Product list* filters. To edit a rule, hover over the record and click the *Edit*  button. To remove a rule, use the *Delete*  button. To clone a rule, click .

HLR request rules na@alarislabs.com


Total: 24 Filter Refresh page Export Add new rule

ID	NAME	CHOICE LIST	PREFIX LIST	PRODUCT LIST
674	453-12	mpn	9111	
670	453-2	mpn	9112	
659	453-3	mpn	9113	

### HLR request rules

To add a new rule, click the *Add new rule* button. Configure the following fields in the window that appears:

×

 **Create new rule**×

Name\*  
Spain TMT

Prefix list\*  
34511120-34511125 ×

Sender ID list  
info × exceder × perfect001 ×

Choice list\*  
mnp ×

mnp

Products inclusive list

Product list  
sa\_company - rest\_of\_the\_world × sa\_company - SMS retail ×

Product type  
h1r ×

Product names  
adv2 ×

✔ SubmitClose

### Create new rule

- *Name*: name of the rule, for example: *Spain TMT*. Mandatory parameter
- *Prefix list*: list of numeric prefixes for which the rule will be activated. The field is mandatory. It is possible to specify a range of prefixes, for example: *34511120-34511125* which includes prefixes *34511120, 34511121, 34511122, 34511123, 34511124, 34511125*. To add a value to the list, press *Enter*.

---

**NOTE:** The length of the range beginning and end must coincide. That is, it is not possible to set a range as *3451112-34511125*. Additionally, an exception can be specified to exclude a particular prefix. For example:

34

!34511120

- *Sender ID list*: list of sender IDs for which the rule will be activated. By default all sender IDs are included in the rule. Alpha, alphanumeric and numeric sender IDs are allowed. Hyphens or blank spaces in sender ID names are allowed. To add a value to the list, press *Enter*.

- *Choice list*: select the HLR provider names. Several providers can be set up in a specific order - once they are selected, the drag&drop window appears to configure the order. In this case, if the first provider does not supply an HLR MCCMNC (or it is impossible to parse it from the provider's response), the next-in-line provider will be inquired

---

**NOTE:** Overlapping rules cannot be created. For example, if 2 rules with empty sender IDs and product IDs (which is "All") for prefix 852 are created, the error will be shown: "Prefix collision error".

---

- *Products inclusive list*: toggle by clicking the  button and specify the list of client products for which the rule will be activated. All products are included by default. Select required products to enable the rule for particular client products. Use the *Filter...* window to insert the product name.
- *Product type*: select the client product type(s). Possible values include *hlr* and *sms*
- *Product names*: select the appropriate client product name(s).

---

**NOTE:** Search for suitable HLR rules has the following prioritization: product ID, product name, sender ID, prefixes.

---

Click the *Submit* button to save the changes or the *Close* button to disregard them. The *Reset* button will reset the configured changes.

## 7 Settings

The page serves to configure global settings (that are applied to all HLR services and clients).

- *Default connection timeout:* timeout (in seconds, default value is 2) to establish a connection with the HTTP HLR service. Positive integer values are allowed
- *Default request timeout:* timeout (in seconds, default value is 2) to expect a response from the HTTP HLR service (if a value is not configured in the *HTTP request timeout* parameter of [Sources](#)<sup>[6]</sup>). Positive integer values are allowed
- *Concurrent request timeout:* timeout (in seconds, default value is 5) to wait for concurrent requests. That is, if several requests to the same number have been received within the timeout, only one request will be dipped through the HLR service. If it provides an HLR MCCMNC, the MCCMNC will be used as cached values for the rest of requests, otherwise the requests will be dipped through the HLR service as well. Positive integer values are allowed
- *Enterprise API hostname:* the address to fetch data (for example, HLR client product IDs) from the database to show it (actual names instead of IDs) in the HLR configurator interfaces such as [HLR request rules](#)<sup>[18]</sup> or [Clients](#)<sup>[12]</sup>. Applicable to the HLR Configurator System which is installed separate from the main Alaris System.

Example: <http://localhost:3006/eapi/>

- *Check global rules for products:* when deselected, HLR request rules with "All" client products are not checked if there is at least one client-based rule. Enabled by default.

**Example:** suppose there are 2 rules:

Rule 1 for prefix 34 and all client products

Rule 2 for prefix 852 and client product ID 45

If the checkbox is deselected and a request from client product ID 45 is received, only Rule 2 can be used (if the request is intended for another prefix - for example, 34, no rule will be used). If the checkbox is selected, both rules can be used (but Rule 2 has a priority over Rule 1).

- *Check global rules for Sender IDs:* when deselected, HLR request rules with "All" sender IDs are not checked if there is at least one client-based rule. Enabled by default.

Example: suppose there are 2 rules:

Rule 1 for prefix 34 and all sender IDs

Rule 2 for prefix 852 and sender ID "Facebook"

If the checkbox is deselected and a request from sender ID Facebook is received, only Rule 2 can be used (if the request is intended for another prefix - for example, 34, no rule will be used). If the checkbox is selected, both rules can be used (but Rule 2 has a priority over Rule 1)

Save the changes with the help of the *Submit* button.


## 8 Users

The *Users* interface serves to create and edit user accounts.

Users		
LOGIN	EMAIL	NAME
Neverly	never@north.net	
Mary	mary@pocodiner.es	Mary Goode
John	john_doe@pocodiner.es	
Pat	pat@pocodiner.es	Patrick Best

### Users

Click *Add new user* to create a new user record.

 **Add new user**
✕

**Login \***  
Dreamer

**Email \***  
dreamer@money.net

**Password \***  
•••••

**First name**  
Dreamer

**Last name**  
Diminuendo

**Page size**  
50

**Role permissions**  
 User\_vieweditpresent\_role × user × tech\_support\_role\_role × default\_d

↻ Reset

✔ Submit
Close

### Add new user

Configure the following fields:

- *Login*
- *Email*
- *Password*
- *First name*




## Users

- *Last name*
- *Page size*: the number of records displayed per page
- *Role permissions*: select the role (created in [Roles](#)<sup>[24]</sup>), the number of available permissions will be displayed in the field.

Click *Reset* to clear the fields. Click *Submit* to save the record and close the form. Click *Close* to close the form without saving.

## 9 Roles

The *Roles* interface serves to create and edit user roles and permission sets.




The screenshot shows the 'Roles' management interface. At the top right, the user 'iana@alarislabs.com' is logged in. Below the header, there is a summary bar showing 'Total: 3' roles, along with buttons for 'Refresh page', 'Export', and 'Add new role'. The main content is a table with three columns: 'ROLE NAME', 'ROLE PERMISSIONS', and 'USER'. The table contains one visible row for the 'admin' role, which has a list of permissions including 'sources.read', 'users.read', 'roles.read', 'clients.read', 'products.read', 'providers.read', 'rules.read', 'sources.read', 'sources.edit', 'settings.read', and 'settings.edit'. The 'USER' column for this role is 'admin'. At the bottom, there is a pagination control showing 'Showing 1 - 3' items, 'Prev', '1', 'Next', and a 'Show rows' dropdown set to '25'.

ROLE NAME	ROLE PERMISSIONS	USER
admin	sources.read sources.edit settings.read  users.read users.edit roles.read roles.edit profile.edit clients.read clients.edit products.read providers.read rules.read rules.edit sources.read sources.edit settings.read settings.edit	admin

### Roles

Click *Add new role* to create a new role record.

×  
 **Add new role**

Role name \*  
user

Role permissions

les.read × roles.edit × settings.edit × sources.edit × sources.read × ^

- users.read
- users.edit
- roles.read
- roles.edit
- profile.edit
- clients.read

### Add new user

Configure the following fields:

- *Role name*
- *Role permissions*: select appropriate permissions for the role from the drop-down list.

Click *Reset* to clear the fields. Click *Submit* to save the record and close the form. Click *Close* to close the form without saving.